TURF-TYPE TALL FESCUE LAWN CALENDAR



College of Agricultural & Environmental Sciences UNIVERSITY OF GEORGIA

	В	<u>B</u>	<u>B</u> est Month		<u>P</u> <u>P</u>		ossible Month		M Ma		arginal Month	
	Jan	Feb	Mar	Apr	May	Jun	Jul	Aug	Sep	Oct	Nov	Dec
⅓ total	OK	OK	OK	OK	OK	OK	OK	OK	OK	OK	OK	OK
v planted noist.	OK	OK	OK	OK	OK	OK	OK	OK	OK	OK	New sod	New sod
il was not		В	В	Р					Р	В	В	
ied at any	В	В	В	Р	Р	Р	Р	Р	Р	Р	В	В
	М	М	В	В	М				Р	В	Р	М
	Р	Р	Р	Р						Р	Р	Р
		Р	Р	М	М				Р	В	Р	
	М	Р	Р	Р					Р	В	Р	М
		В	Р	Р	М				Р	В	Р	
eeds are e used. and other	В	В	В	Р	М				Р	В	В	В
		В	В	Р								
af plants etc.	OK	OK	ОК	ОК	OK	OK	OK	ОК	ОК	ОК	ОК	ОК
crabgrass, urf.					Р	Р	М	М				
inter awn is to be s.									В	Р		

Mowing Height:

 $2^{"} - 3^{"}$ raise $\frac{1}{2}$ " higher in hot weather. Remove no more than $\frac{1}{3}$ total height at one time.

Water:

1" per week if no rainfall. 30 days watering allowed for newly planted sod or seed. Sod laid in fall or winter months should be kept moist.

Fertilization: 2 – 4 lbs N/1000 ft²/YR

Follow fertilizer recommendations on soil test report. If the soil was not tested, use any turf fertilizer and follow label rates.

Ideal pH Range: 5.5 – 6.5

Use dolomitic lime per soil test recommendation. Can be applied at any time.

Aeration:

Use a core aerator during active growth season.

Dethatch: Generally not necessary.

Seeding – New Lawn*:

5 - 6 lbs per 1000 ft².

Interseeding-Established Lawns*:

3 - 5 lbs seed per 1000 ft².

Sodding:

Sod may not be available in all months of the year.

Weed Control:

Read product label carefully to determine which weeds are controlled and on which grasses the product can be used. **Spring preemergence*** prevents crabgrass, goosegrass, and other summer weeds.

Broadleaf postemergence* spot spray to control broadleaf plants like chickweed, wild violet, dandelion, wild onion, etc.

Grassy weed postemergence* control grassy weeds like crabgrass, dallisgrass, etc. Do not apply to drought-stressed turf.

Winter preemergence* prevents chickweed and other winter weeds. Do not apply preemergence herbicides if lawn is to be seeded, interseeded, or sodded within 3 to 4 months.

* Read weed control product labels carefully. Some products cannot be applied within a few weeks of establishment.